

AD-A116 112

ARMY ELECTRONICS RESEARCH AND DEVELOPMENT COMMAND FO--ETC F/G 9/2
A HANDHELD CALCULATOR (HHC) PROGRAM FOR THERMAL IMAGING TARGET --ETC(U)
JAN 82 J R MOULTON, G H KORNFIELD

UNCLASSIFIED

DELNV-TR-0030

NL

1 75
ALIA
17-6112

END
DATE
FILMED
10-7-82
DTIC



1.0



1.1



1.25



1.4



1.6

2.8

2.5

2.2



2.0



1.8

MICROCOPY RESOLUTION TEST CHART
NATIONAL BUREAU OF STANDARDS-1963-A

AD A116112

AD

Report DELNV-TR-0030

A HANDHELD CALCULATOR (HHC) PROGRAM FOR
THERMAL IMAGING TARGET ACQUISITION ANALYSIS

— A USER'S GUIDE

by
Joseph R. Moulton
and
Gertrude H. Kornfeld

January 1982

Approved for public release; distribution unlimited.

DTIC FILE COPY

U.S. ARMY ELECTRONICS R&D COMMAND
NIGHT VISION & ELECTRO-OPTICS LABORATORIES
FT. BELVOIR, VIRGINIA 22060



**Destroy this report when it is no longer needed.
Do not return it to the originator.**

**The citation in this report of trade names of
commercially available products does not constitute
official endorsement or approval of the use of such
products.**

UNCLASSIFIED

SECURITY CLASSIFICATION OF THIS PAGE (When Data Entered)

REPORT DOCUMENTATION PAGE		READ INSTRUCTIONS BEFORE COMPLETING FORM
1. REPORT NUMBER DELNV-TR-0030	2. GOVT ACCESSION NO. AD-A112112	3. RECIPIENT'S CATALOG NUMBER
4. TITLE (and Subtitle) A HANDHELD CALCULATOR (HHC) PROGRAM FOR THERMAL IMAGING TARGET ACQUISITION ANALYSIS - A USER'S GUIDE		5. TYPE OF REPORT & PERIOD COVERED Technical Report
		6. PERFORMING ORG. REPORT NUMBER
7. AUTHOR(s) Joseph R. Moulton Gertrude H. Kornfeld		8. CONTRACT OR GRANT NUMBER(s)
9. PERFORMING ORGANIZATION NAME AND ADDRESS US Army Electronics Research and Development Command; Night Vision & Electro-Optics Laboratory; ATTN: DELNV-V, Fort Belvoir, VA 22060		10. PROGRAM ELEMENT, PROJECT, TASK AREA & WORK UNIT NUMBERS
11. CONTROLLING OFFICE NAME AND ADDRESS US Army Electronics Research and Development Command; Night Vision & Electro-Optics Laboratory; ATTN: DELNV-V, Fort Belvoir, VA 22060		12. REPORT DATE January 1982
		13. NUMBER OF PAGES 43
14. MONITORING AGENCY NAME & ADDRESS (if different from Controlling Office)		15. SECURITY CLASS. (of this report) Unclassified
		15a. DECLASSIFICATION/DOWNGRADING SCHEDULE
16. DISTRIBUTION STATEMENT (of this Report) Approved for public release; distribution unlimited.		
17. DISTRIBUTION STATEMENT (of the abstract entered in Block 20, if different from Report)		
18. SUPPLEMENTARY NOTES		
19. KEY WORDS (Continue on reverse side if necessary and identify by block number) Thermal Imaging Systems Field Performance Pocket Calculator Environmental Effects		
20. ABSTRACT (Continue on reverse side if necessary and identify by block number) The proliferation of thermal imaging sensors to most major weapon platforms has broadened the need for FLIR performance analysis capability throughout the Army. To date, the Army analysis capability has been concentrated within the Visionics Division of the Night Vision and Electro-Optics Laboratory except for the target acquisition codes that have been incorporated within the Army Wargames. This report describes one of several activities of NV&EOL to disseminate analysis capability to a broad spectrum of (Continued)		

DD FORM 1 JAN 73 1473

EDITION OF 1 NOV 65 IS OBSOLETE

UNCLASSIFIED

SECURITY CLASSIFICATION OF THIS PAGE (When Data Entered)

UNCLASSIFIED

SECURITY CLASSIFICATION OF THIS PAGE(When Data Entered)

(Block 20. (Continued))

Army elements so that each may undertake independently routine FLIR performance calculations as required. Although these analytical models are incorporated entirely within a handheld calculator (HHC) and designed for simplicity in their use, they provide a comprehensive performance analysis capability. This capability stems from unique analytical fits to higher level models and from the remarkable capacity of the new HP 41CV programmable handheld calculator. This report provides a complete user's guide in the application of HHC programs to FLIR analysis problems for requirements frequently encountered by FLIR and weapon platform designers, applications analysis, tacticians, and battle-field commanders. A companion report that provides a technical description of this work is in progress. Operation of the HHC requires minimal instruction and all actions of the operator are prompted by displayed alphanumeric inquiries. Target acquisition analysis under adverse weather are routinely computed using this HHC model, providing ranges for detection, classification, recognition and identification for a variety of US and Warsaw Pack Armor vehicles. The model enables the user to quickly determine search times for a given search sector as well as target acquisition probabilities for weather and signature conditions specified. Atmospheric transmission in the 8-12 μm and visual spectral region can be routinely determined for any specified range based on an abbreviated form of LOW-TRAN V, EO SEAL and G/AP atmospheric models.



A

UNCLASSIFIED

SUMMARY

The proliferation of thermal imaging sensors to most major weapon platforms has broadened the need for FLIR performance analysis capability throughout the Army. To date, the Army analysis capability has been concentrated within the Visionics Division of the Night Vision and Electro-Optics Laboratory except for the target acquisition codes that have been incorporated within the Army Wargames. This report describes one of several activities of NV&EOL to disseminate analysis capability to a broad spectrum of Army elements so that each may undertake independently routine FLIR performance calculations as required. Although these analytical models are incorporated entirely within a handheld calculator (HHC) and designed for simplicity in their use, they provide a comprehensive performance analysis capability. This capability stems from unique analytical fits to higher level models and from the remarkable capacity of the new HP 41CV programmable handheld calculator.

This report provides a complete user's guide in the application of HHC programs to FLIR analysis problems for requirements frequently encountered by FLIR and weapon platform designers, applications analysis, tacticians, and battlefield commanders. Operation of the HHC requires minimal instruction and all actions of the operator are prompted by displayed alphanumeric inquiries. Target acquisition analysis under adverse weather are routinely computed using this HHC model, providing ranges for detection, classification, recognition and identification for a variety of US and Warsaw Pact Armor vehicles. The model enables the user to quickly determine search times for a given search sector as well as target acquisition probabilities for weather and signature conditions specified. Atmospheric transmission in the 8-12 μm and visual spectral region can be routinely determined for any specified range based on an abbreviated form of LOWTRAN V, EO SAEL and G/AP atmospheric models.

A companion report¹ now in progress provides a technical description of the HHC algorithms used as well as the technical genesis of the analytical forms. In general, the performance model is based on the Johnson Criteria,² as applied to analytical equations similar to those described by Ratches et al.³ for static range performance, and by Lawson.

¹ G. Kornfeld and J. R. Moulton, *Technical Description of HHC Target Acquisition Program (TGT ACQ)* (In Progress).

² J. Johnson, *Analysis of Image Forming Systems*, Proceedings of the Image Intensifier Symposium (1958).

³ J. A. Ratches, W. R. Lawson, L. P. Obert, R. J. Bergmann, T. W. Cassidy, and J. M. Swenson, *Night Vision Laboratory Static Performance Model for Thermal Viewing Systems*, USA Electronics Command Report ECOM-7043 (April 1975).

Cassidy and Ratches⁴ for search time performance. The basis for the atmospheric analysis stems from analytical fits to LOWTRAN V,⁵ by Kornfeld⁶ and the NVL G/AP Aerosol Data Base⁷ by Shields.⁸ All atmospheric algorithms used in the HHC program are believed to be similar to those in the current version of EO SAEL.⁹ The thermal imagers listed in this user's guide as sensors 1 through 4 are identified in the Visionics Performance Handbook¹⁰ by Obert et al.

⁴ W. R. Lawson, T. W. Cassidy and J. A. Ratches, *A Search Model*, IRIS Specialty Group on Imaging, Naval Academy, Annapolis, MD, June 78 (Confidential).

⁵ F. X. Kneizys, *Atmospheric Transmittance/Radiance: Computer Code LOWTRAN 5*, AFGL-TR-80-0067, February 1980.

⁶ G. Kornfeld, *A LOWTRAN Equivalent Computer Program*, NV&EOL internal report, February 1981.

⁷ J. R. Moulton, R. J. Bergemann, and M. C. Sola, (S) *European Winter Atmospheric Environment (U)*, IRIS Proceedings (August 1976).

⁸ F. J. Shields, Internal NV&EOL DF, subject: *NV&EOL G/AP Aerosol Atmospheric Models* (7 September 1978).

⁹ Louis D. Duncan, editor, *EOSAEL 80, Vol. I: Technical Documentation*, Atmospheric Sciences Laboratory Report ASI-TR-0072, January 1981.

¹⁰ L. P. Obert, J. T. Wood, C. J. Nash, (C) *Visionics EO Sensor Performance Handbook VOL. I (Natural European Environments) (U)*, June 1981.

CONTENTS

Section	Title	Page
	SUMMARY	iii
	ILLUSTRATIONS	vi
	TABLES	vii
	METRIC CONVERSION FACTORS	viii
I	INTRODUCTION	1
II	OVERVIEW OF HHC TARGET ACQUISITION MODEL	5
III	ILLUSTRATIVE APPLICATIONS OF HHC ANALYSIS	10
	APPENDIX – TGT_ACQ PROGRAM LISTING	17

ILLUSTRATIONS

Figure	Title	Page
1	HP 41CV HHC Hardware Used for Thermal Imager Performance Analysis	2
2	Closeup of HHC Hardware Keyboard	3
3	Mode Keys with Display (insufficient registers)	4


TABLES

Table	Title	Page
1	TGT_ACQ Program Responses	8
2	TGT_ACQ Analysis Number Responses	10
3	Predicted Range Performance	12
4	Predicted Search Time and Recognition Probability	12
5	Predicted Recognition Performance Versus MRTs and Transmission	13
6	Display Listing for Range Performance Example	14
7	Display Listing for Different MRT Example	15
8	Display Listing for Atmospheric Data Example	16

METRIC CONVERSION FACTORS

Approximate Conversions to Metric Measures

Symbol	When You Know	Multiply by	To Find	Symbol
LENGTH				
in	inches	2.5	centimeters	cm
ft	feet	30	centimeters	cm
yd	yards	0.9	meters	m
mi	miles	1.6	kilometers	km
AREA				
in ²	square inches	6.5	square centimeters	cm ²
ft ²	square feet	0.09	square meters	m ²
yd ²	square yards	0.8	square meters	m ²
mi ²	square miles	2.6	square kilometers	km ²
	acres	0.4	hectares	ha
MASS (weight)				
oz	ounces	28	grams	g
lb	pounds	0.45	kilograms	kg
	short tons (2000 lb)	0.9	metric ton	t
VOLUME				
tsp	teaspoons	5	milliliters	ml.
Tbsp	tablespoons	15	milliliters	ml.
in ³	cubic inches	16	milliliters	ml.
fl oz	fluid ounces	30	milliliters	ml.
c	cups	0.24	liters	L
pt	pints	0.47	liters	L
qt	quarts	0.95	liters	L
gal	gallons	3.8	liters	L
ft ³	cubic feet	0.03	cubic meters	m ³
yd ³	cubic yards	0.76	cubic meters	m ³
TEMPERATURE (exact)				
°F	degrees Fahrenheit	5/9 (after subtracting 32)	degrees Celsius	°C



**Approximate Conversions
from Metric Measures**

Symbol	When You Know	Multiply by	To Find	Symbol
LENGTH				
mm	millimeters	0.04	inches	in
cm	centimeters	0.4	inches	in
m	meters	3.3	feet	ft
m	meters	1.1	yards	yd
km	kilometers	0.6	miles	mi
AREA				
cm ²	square centimeters	0.16	square inches	in ²
m ²	square meters	1.2	square yards	yd ²
km ²	square kilometers	0.4	square miles	mi ²
ha	hectares (10 000 m ²)	2.5	acres	
MASS (weight)				
g	grams	0.035	ounces	oz
kg	kilograms	2.2	pounds	lb
t	metric ton (1000 kg)	1.1	short tons	
VOLUME				
mL	milliliters	0.03	fluid ounces	fl oz
mL	milliliters	0.06	cubic inches	in ³
L	liters	2.1	pints	pt
L	liters	1.06	quarts	qt
L	liters	0.26	gallons	gal
m ³	cubic meters	35	cubic feet	ft ³
m ³	cubic meters	1.3	cubic yards	yd ³
TEMPERATURE (exact)				
°C	degrees Celsius	9/5 (then add 32)	degrees Fahrenheit	°F

A HANDHELD CALCULATOR (HHC) PROGRAM FOR THERMAL IMAGING

TARGET ACQUISITION ANALYSIS — A USER'S GUIDE

1. INTRODUCTION

Thermal Imaging Sensors, often referred to as FLIRs are incorporated into most major Army weapon platforms to provide target acquisition capability under day/night, semi-adverse weather and obscured battlefield conditions. The acquisition capability provided by thermal imagers is dependent upon many factors: i.e., sensor parameters, target range, target type, target history, weather type, intensity and duration, operator training, terrain structure, tactical employment, etc. The calculations of this target acquisition capability has been, heretofore, performed by analysts highly trained in thermal imaging, environmental and computer technologies. The objective of this effort is to provide the typical user of thermal imager analysis, whether he be a weapons developer, TRADOC tactician or FLIR developer, the capability of carrying out performance analysis independently at his desk after a few minutes tutorial. The analysis equipment (HHC) is a Hewlett Packard 41CV Handheld Calculator with or without a HP 82143A printer that has been programmed with unique performance algorithms developed at the Night Vision and Electro-Optics Laboratory. These performance algorithms are for the most part condensed versions of large scale computer programs currently used with a computer main frame. Although the HHC program is currently limited to thermal imaging sensors, future versions will address target acquisition analysis of day optics and television sensors as well.

Although the HHC equipment and algorithms are unclassified, programs are of such design that when used in conjunction with classified sensor parameters, classified target acquisition analysis can be performed as well. Discretion is required, however, on the part of the user to insure that analysis results are properly protected whenever classified sensors are considered.

In addition to this Introduction section, this report contains sections that describe the design and application of this analysis tool for a variety of target acquisition problems. Taken in their entirety, these sections serve as a user's guide for conducting thermal imaging analysis using the HHC target acquisition model. Specifically, Section II gives a description of the HP 41CV hardware and an overview description of the program. As described, the programs are executed interactively with the HHC operator using the full alphanumeric capability of the HP 41CV. Responses to the HHC's inquiries not readily known by the operator are listed in this section. A more detailed description of the HHC

hardware is provided by the manufacturer.¹¹ In addition, a full technical description of the algorithms is provided.¹¹ Section III gives illustrative examples of using the HHC to obtain the target acquisition capability for a typical thermal imager as well as performance variations one could expect for a variety of weather conditions. The examples used enable one to calculate the range dependent target acquisition capability of detection, classification, recognition and identification for the thermal sights under the weather conditions considered. Further, the examples illustrate the probability of accomplishing this range dependent target acquisition and the search time required for a given search field of view. In addition, examples are given that enable one to calculate atmospheric propagation in the 8- to 12- μm spectral band for different weather conditions and ranges. The atmospheric propagation calculations allow the user to better understand the atmospheric influence on target acquisition performance.

The HHC hardware is shown in Figure 1, illustrating the HP 41CV Handheld Calculator with the magnetic card reader HP 82104A and alphanumeric printer HP 82143A. A plug-in module (not shown) called a STAT PAC can be used for input data preparations.



Figure 1. HP 41CV HHC hardware used for thermal imager performance analysis.

¹¹ Hewlett Packard, *The HP-41C/41CV Alphanumeric Full Performance Programmable Calculator, Owner's Handbook and Programming Guide*, September 1980.

The HP 41CV is a commercially available handheld calculator that provides considerable computational capability to the user even without the Target Acquisition Model. This capability is fully described in the HP 41CV Owner's Handbook and Programming Guide that is provided with the calculator, hence will not be repeated in this report. As shown in Figure 1, the printer is connected to the calculator via a single cable, whereas the magnetic card reader is attached to the calculator as a plug-in attachment. The Target Acquisition Model is written on magnetic cards that are read into the HHC using the card reader. The HP 41CV has continuous memory that preserves the program even after the HHC has been turned off; hence, once read, most users will rarely require additional card reading. Card reading will only be required when the Target Acquisition Model has been cleared from the HHC.

The printer and the HHC each contain rechargeable battery packs; hence, operation in remote field sites without d.c. power is no problem. A battery charging element is provided for the calculator and the printer that enables operation from US standard d.c. current as well.

A closeup of the HP 41CV HHC keyboard is shown in Figure 2. Once the program is loaded in the HHC, the operator uses only the On, User, A, number key 0 to 9, and the Run Key identified as R/S. As will be described in the following paragraphs, the response requirements by the user are generally limited to numerical keys 0 to 9, decimal dot, and R/S keys once the On, User, and letter keys have been executed.




Figure 2. Closeup of HHC hardware keyboard.

The user of the HHC for target acquisition analysis should first acquaint himself with the basic keyboard functions and display modes. The keyboard has 3 color schemes as follows:

White Key Lettering —	Normal functions activated by key selection.
Gold Key Lettering —	2nd level function activated by first striking gold key (shift), then hitting desired key.
Blue Key Lettering —	Alphanumeric functions activated by first striking ALPHA key, then hitting desired key. For numbers and small letters, strike gold shift key when in ALPHA mode.
White Mode Key (Top) — (Figure 3)	On turns calculator on. On again turns calculator off. User selects user mode. User again removes user mode. PRGM selects program mode. <i>Do not select PRGM mode except for card writing; otherwise, modification of TGT__ACQ Program may result. PRGM again removes PRGM. (Note: __ represents a space.)</i> ALPHA selects alphanumeric mode. ALPHA again removes ALPHA.




Figure 3. Mode keys with display (insufficient registers).

The STAT PAC is a small application module that inserts into the top of the 41CV calculator that allows curve fitting of FLIR MRT data required as an input to the TGT__ACQ Program.

The Peripheral Printer keyboard is self-explanatory. Normal mode of usages is On, Dark, and Normal switch positions. Paper is advanced by striking Paper Advance Key. The Print Key prints whatever is displayed on the HHC display. Caution is required when in the PRGM mode since these keys insert print or advance instruction in the TGT__ACQ Program.

II. OVERVIEW OF HHC TARGET ACQUISITION MODEL

The target acquisition algorithms described in this section have been developed for use in conjunction with the Hewlett Packard 41CV Handheld Calculator for the purpose of enabling the user to carry out thermal imager performance analysis independently at his desk or remote field site with as little as minutes of instruction. Target acquisition analysis capability provided include range, probability, and search time for the mission tasks of detection, classification, recognition, and identification. The algorithms are programmed into the 41CV in a manner to simplify user-response by taking full advantage of the alphanumeric capability of the HP 41CV. For the most part, the user need only answer the displayed inquiry of the HHC which he does by pressing numerical keys, then the R/S key. Because of these continuing displayed interrogatives, the user concentrates his attention on the analysis task instead of the mechanics of operating the HHC. In other words, the HHC keeps track of the mechanics of analysis so that the user can concentrate on understanding the analysis.

There are three elements associated with the HHC Performance Models, which are:

- HP 41CV Calculator and Peripherals (hardware).
- Target Acquisition and Atmospheric Program (software on magnetic cards).
- User's Guide (this report).

The User's Guide is this report, hence needs no further explanation. The other two elements will be described as follows:

HP 41CV CALCULATOR AND PERIPHERALS

The HP 41CV hardware consists of the following:

- HP 41CV Handheld Calculator.
- HP 82143A Peripheral Printer.
- HP 82104A Card Reader.
- HP 00041 — 14001 (15002) STAT PAC.
- HP 00097 — 13143 120 Blank Cards.

The HHC Target Acquisition Program is coded on 7 magnetic cards under the title of TGT__ACQ.

PROGRAM TGT__ACQ LOADING

As mentioned previously, the Target Acquisition Program entitled TGT__ACQ is written on 7 magnetic cards. These cards are read into the HHC as follows:

- Allocate 30 data registers XEQ ALPHA SIZE ALPHA 030.
- Check for availability of at least 207 program registers PRGM GTO . . . Displayed number is available registers.

If insufficient program registers are available, clear existing programs as follows:

Catalog 1 displays existing program names XEQ ALPHA CLP ALPHA. ALPHA (Key in program name) ALPHA.

- *Without* being in the PRGM Mode, insert each card twice into the card reader, once in each direction. The display indicates RDY nn of 13 each time with nn being the lowest numbered card yet to be read. Repeat card side if error message is displayed. Upon completion of last card, working is displayed.

- Test execution of TGT__ACQ by:

User Mode, Σ — (i.e., strike "Shift" Key then "V" Key; Printer? is displayed if program is properly loaded.).

EXECUTING TGT__ACQ PROGRAM

The following description assumes the seven magnetic cards containing the Target Acquisition Analysis Program TGT__ACQ has been read into the HHC and turned on. Further the HHC has been put in the "User" mode, and "PRGM" or "ALPHA" mode was not selected. Upon striking the "Shift" and "A" Key, the HHC takes command and prompts the user as to each subsequent action through interactive inquiries. The user responds to the inquiries by key striking an appropriate numerical value then executes by striking the Run/Stop Key identified as "R/S." For example, after striking "Shift" and "A," the inquiry "Printer?" is displayed. The user responds by striking the 1 Key and the R/S Key if the printer is hooked to the HP 41CV. If not, the user strikes 0, R/S. Hence 1 = yes and 0 = no and R/S implements.

The specific inquiries presented to the HHC user are described in Table 1.

The matrix codes allow the user to obtain the target acquisition performance for each of the five discrimination tasks (Easy Detection, Cluttered Detection, Classification Recognition, and Identification) by entering either "20," "30," or "40," then "R/S." If only one target acquisition performance is desired, say Recognition Probability, the user selects the appropriate matrix code, i.e., 34 for Recognition Probability. After the target acquisition performances are displayed, the HHC returns to the "change?" inquiry. The matrix code used in conjunction with the change inquiry allows the user to rapidly parameterize target acquisition performance as a function of the battlefield environment.

There is one additional response to the Analysis No.? inquiry, being 97.

97	Upon keying in 97 or TR in Blue Keys, meaning transmission, the HHC asks the range for which the transmission is to be
Range?	calculated. User responds with range in km, then R/S.

Table 1. TGT-ACQ Program Responses

No. HHC Display	User Response Options
Printer?	1 = Yes, 0 = No
1 Sensor?	1 = NFOV ¹² 2 = WFOV ¹² 3 = NFOV ¹² 4 = WFOV ¹² 5 = New FLIR (See MRT Data preparations using STAT PAC instructions later in this section)
HORZ FOV?	Key in value for New FLIR in degrees
a value?	Key in a value of MRT curve fit
b value?	Key in b value of MRT curve fit
2 DELTA T?	Key in value of target ΔT in °C
3 Target No.?	1 = M113 2 = M60A1, 3 = M60A1 Hulldown 4 = M109, 5 = M109 Hulldown 6 = M551, 7 = M551 Hulldown 8 = DIVAD, 9 = DIVAD Hulldown 10 = T-62, 11 = T-62 Hulldown 12 = T-72, 13 = T-72 Hulldown 14 = T-64, 15 = T-64 Hulldown 16 = ZSU, 17 = ZSU Hulldown
4 ACQ PROB?	Value of probability of acquisition desired (0.0 to 1.0)
5 Weather?	1 = Clear, Hazy or Foggy 2 = Rain with Haze or Fog
6 Visual RG?	Value of visual range desired in km (0.0 to 50.0 km)
7 Rel Humid?	Value of Relative Humidity desired (0.0 to 1.0)
8 Air Temp?	Value of air temperature desired in degrees Celsius (°C)
Rain Rate?	Rain rate desired in mm/h (1.0 to 50 mm/w)

¹² L. P. Obert, J.T. Wood, C. J. Nash, (C) *Visionics F/O Sensor Performance Handbook VOL I (Natural European Environments)*, Pages 5-2/4 and 5-6 (1), June 1981.

Table 1. TGT_ACQ Program Responses (Cont'd)

No. HHC Display	User Response Options
Changes?	One number 1 to 8 if any of the above responses need changed. If no changes are necessary, press R/S.
Analysis No.?	There are a variety of target acquisition analysis possible that can be selected by number. The specific analysis is requested using the matrix code in Table 2.
Search FOV? Range? What PROB?	Upon selection of the Matrix Code 40-45, the inquiries are generated for the user to answer in sequence. For the search FOV, the user enters the horizontal search field in degrees, then depresses "R/S." The range inquiry is answered by keying in the target range in km. The target acquisition probability for unlimited time (MAX PROB) is then displayed followed by what PROB? The user then selects a detection probability less than the value of MAX PROB shown in decimal fraction. Upon depressing the "R/S" Key, the HHC then gives the time to accomplish the target acquisition function for the search FOV and level of certainty (probability) requested.
Range?	User selection of Matrix Codes 30 to 35 generates this inquiry. The user enters the range in km (nearest tenth) to the target for which the probability is to be determined, and depresses "R/S."

Table 2. TGT-ACQ Analysis Number Responses

Matrix Codes	21	22	23	24	25
20	Easy Detection Range	Cluttered Detection Range	Classification Range	Recognition Range	Identification Range
	31	32	33	34	35
30	Easy Detection Probability	Cluttered Detection Probability	Classification Probability	Recognition Probability	Identification Probability
	41	42	43	44	45
40	Time to Easy Detection	Time to Clutter Detection	Time to Classify	Time to Recognize	Time to Identify

ANALYSIS OF NEW FLIRS

If the user selected 5 as his response to the 1 Sensor? inquiry, he needs to determine the a and b values that are requested by the HHC. These a and b values are found from the new FLIR MRT data using the HHC with the STAT PAC inserted by keying the HHC as follows:

NEQ ALPHA CL Σ E X P ALPHA

A chime sounds when the HHC is ready for the MRT data. The MRT is entered in pairs of value. The first value is the spatial frequency which is keyed in and followed by striking the Enter Key. The second value keyed in is the ΔT for that spatial frequency followed by striking the "A" Key. Continue this process with the next MRT data point of spatial frequency and MRT value, and the next, etc., until all MRT data is entered. When completed, press "E" and the HHC prints out the a and b values. In addition to the a and b value, the correlation coefficient of Fit, R^2 , is provided the user. Also, the HHC provides the MRT value for any spatial frequency when the user keys in the spatial frequency an F follows with striking the R/S Key. The MRT value displayed is for the curve fitted MRT data.

The above a and b values are used to respond to the inquiries when the user has selected a new FLIR: i.e., answered the question Sensor? (Step 1) with 5.

III. ILLUSTRATIVE APPLICATIONS OF HHC ANALYSIS

The HHC Program named TGT__ACQ is listed in the Appendix in its entirety. Several examples of the application of TGT__ACQ to target acquisition analysis are provided in this section. The examples are:

Case I — FLIR Range Performance (Table 3).

Case II — Search Time and Recognition Probability (Table 4).

Case III — Performance vs MRTs and Transmission (Table 5).

Case I. FLIR Range Performance.

The range performance for Sensor 1 as a function of visual range was calculated and the results summarized in Table 3. A copy of the display was printed and is provided in Table 6. The summary table shows the degrading part of FLIR target acquisition performance as the visibility diminishes. Note this example used the Matrix Code 20 to obtain the value of each of the five target acquisition tasks.

Case II. Search Time and Recognition Probability.

This example continues with the same sensor and weather conditions used in Case I, but *illustrates the use of Matrix Codes 34 and 41*. Had one used the Matrix Code 30 and 40, the search time and recognition probability would have been obtained for all 5 target acquisition tasks as in Case I. The ability to select the specific target acquisition task of interest saves considerable time when one is weather parameterizing various target acquisition task performances. The summary of the results of Case II is given in Table 4 and the display printout is listed in Table 6. The search time remains at a constant value for the visibilities of 7, 3, and 1 km since the detection probability is 1 for those conditions. The probability drops from 1 for the low visibility of 0.5 km, thus increasing the search time at that point.

Case III. Recognition Performance Versus MRTs and Transmission.

As shown in Tables 7 and 8, this case illustrates the HHC Programs ability to analyze different MRTs using data available to the user. The MRT data is keyed into, as described in Section II using the STAT PAC for new FLIR analysis. In addition, this case selected Analysis No. 97; i.e., the mode that produces the 8- to 12- μ m transmission for any range requested. Table 5 provides a summary of the data obtained for the weather conditions given.

The above three cases serve to illustrate the breadth of analysis possible using the HHC TGT__ACQ Program. Many other and more detailed target acquisition analyses are possible. If in the process of such analysis any program errors are discovered, the user is requested to contact the Systems Analysis Team, Visionics Division of the Night Vision and Electro-Optics Laboratory at (703) 664-5843 or Autovox 354-5843.

Table 3. Predicted Range Performance

Visual Range (km)	Easy Det	Clut Det	Class	Rec	ID
7.0	20.96	8.96	5.10	2.74	1.43
3.0	18.45	8.47	4.94	2.69	1.41
1.0	6.89	4.80	3.41	2.17	1.25
0.5	2.06	1.82	1.58	1.25	0.88

Conditions

Sensor = 1.0
Delta T = 5.0
Target # = 12.0
ACQ PROB = 0.5

Weather = 1.0
Rel Humid = 0.90
Air Temp = 10.0
Visual Range = as indicated

Table 4. Predicted Search Time and Recognition Probability

Visual Range (km)	2 km REC PROB.	2 km Search Time (s)
7.0	0.78	30.74
3.0	0.77	30.74
1.0	0.59	30.74
0.5	0.002	40.94

Conditions

Sensor = 1.0
Delta T = 5.0
Target # = 12.0
ACQ PROB = 0.5

Weather = 1.0
Rel Humid = 0.90
Air Temp = 10.0
Visual Range = as indicated

Search FOV = 30 deg
Range = 2.0 km

Table 5. Predicted Recognition Performance Versus MRTs and Transmission

Visual Range (km)	MRT #1 REC (W/O Rain)	MRT #2 REC		0.5 km Transmission	
		(W/O Rain)	(W/Rain)	8-12 km	Visual
7.0	3.74	2.74	1.88	.59	.50
3.0	3.65	2.69	1.80	.56	.34
1.0	2.74	2.17	1.14	.25	.09
0.5	1.42	1.25	0.60	.03	.01

Conditions

Sensor = 1 and 5
Delta T = 5.0
Target # = 12.0
ACQ PROB = 0.5
Rain Rate = 5 mm/h

Weather = 1.0
Rel Humid = 0.90
Air Temp = 10.0
Visual Range = as indicated

Table 6. Display Listing for Range Performance Example

PRINTED	AEQ -TOT HOP	CHANGES?	RUN	CHANGES?	RUN	ANALYSIS NO?	CHANGES?	RUN	ANALYSIS NO?	CHANGES?	RUN	ANALYSIS NO?	CHANGES?	RUN
1 SENSOR	1.00	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
2 DELTA T	1.00	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
3 TARGET NO.	5.00	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
4 ACD PROB?	12.00	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
5 WEATHER?	5.0	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
6 VISUAL F?	1.00	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
7 FEL HOP?	7.00	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
8 GIP TEMP?	10.00	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
CHANGES?		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
ANALYSIS NO?	20.00	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
DETECTED		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
RANGE 6.69		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
CLUT DETECT		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
RANGE 4.00		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
CLASSIFIED		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
RANGE 3.41		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
RECOGNIZED		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
RANGE 2.17		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
IDENTIFIED		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
RANGE 1.25		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
CHANGES?		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
6 VISUAL F?	6.00	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
6 VISUAL F?	3.00	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
CHANGES?		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
ANALYSIS NO?	20.00	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
DETECTED		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
RANGE 16.45		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
CLUT DETECT		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
RANGE 1.72		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
CLASSIFIED		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
RANGE 1.00		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
RECOGNIZED		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
RANGE 1.25		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
IDENTIFIED		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
RANGE 0.69		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
CHANGES?		=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
6 VISUAL F?	6.00	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====
6 VISUAL F?	1.00	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====	=====

APPENDIX -- TGT-ACQ PROGRAM LISTING

```

14*LBL 01
DE FL OF 02 R
*PROMPT-- PROMPT X=0
SF 01 XEQ 09 XEQ 00
XEQ 01 XEQ 02 XEQ 03
STO 10
15*LBL 02
*1 SENSOR-- PROMPT
STO 03 STO IND 03
20*LBL 03
2.7 STO 24 3.57
STO 25 .97 STO 26 FIN
25*LBL 04
2.8 STO 24 3.54
STO 25 2.883 STO 26
FIN
30*LBL 05
5 STO 24 3.51 STO 25
.76 STO 26 FIN
40*LBL 06
15 STO 24 3.51 STO 25
2.29 STO 26 FIN
50*LBL 07
*H02 F07*
50*LBL 08
PROMPT STO 24
*3 VALUE-- PROMPT IN
GAS STO 25 *B VALUE*
PROMPT STO 26 FIN
60*LBL 09
*3 TARGET NO.-- PROMPT
STO 12 STO IND 12
70*LBL 10
2.02 STO 13 FIN
75*LBL 02
3.27 STO 13 FIN
79*LBL 03
1.31 STO 13 FIN
83*LBL 04
3.06 STO 13 FIN
87*LBL 05
1.15 STO 13 FIN
91*LBL 06
2.27 STO 13 FIN
95*LBL 07
.76 STO 13 FIN
99*LBL 08
3.8 STO 13 FIN
103*LBL 09
2 STO 13 FIN
107*LBL 10
2.4 STO 13 FIN
111*LBL 11
.8 STO 13 FIN
115*LBL 12
2.27 STO 13 FIN
119*LBL 13
1.00 STO 13
123*LBL 14
.87 STO 13 FIN
127*LBL 15
1.25*LBL 16
3.8 STO 13 FIN
131*LBL 17
1.74 STO 13 FIN
135*LBL 18
1.74 STO 13 FIN
139*LBL 19
1.74 STO 13 FIN
143*LBL 20
1.74 STO 13 FIN
147*LBL 21
1.74 STO 13 FIN
151*LBL 22
1.74 STO 13 FIN
155*LBL 23
1.74 STO 13 FIN
159*LBL 24
1.74 STO 13 FIN
163*LBL 25
1.74 STO 13 FIN
167*LBL 26
1.74 STO 13 FIN
171*LBL 27
1.74 STO 13 FIN
175*LBL 28
1.74 STO 13 FIN
179*LBL 29
1.74 STO 13 FIN
183*LBL 30
1.74 STO 13 FIN
187*LBL 31
1.74 STO 13 FIN
191*LBL 32
1.74 STO 13 FIN
195*LBL 33
1.74 STO 13 FIN
199*LBL 34
1.74 STO 13 FIN
203*LBL 35
1.74 STO 13 FIN
207*LBL 36
1.74 STO 13 FIN
211*LBL 37
1.74 STO 13 FIN
215*LBL 38
1.74 STO 13 FIN
219*LBL 39
1.74 STO 13 FIN
223*LBL 40
1.74 STO 13 FIN
227*LBL 41
1.74 STO 13 FIN
231*LBL 42
1.74 STO 13 FIN
235*LBL 43
1.74 STO 13 FIN
239*LBL 44
1.74 STO 13 FIN
243*LBL 45
1.74 STO 13 FIN
247*LBL 46
1.74 STO 13 FIN
251*LBL 47
1.74 STO 13 FIN
255*LBL 48
1.74 STO 13 FIN
259*LBL 49
1.74 STO 13 FIN
263*LBL 50
1.74 STO 13 FIN
267*LBL 51
1.74 STO 13 FIN
271*LBL 52
1.74 STO 13 FIN
275*LBL 53
1.74 STO 13 FIN
279*LBL 54
1.74 STO 13 FIN
283*LBL 55
1.74 STO 13 FIN
287*LBL 56
1.74 STO 13 FIN
291*LBL 57
1.74 STO 13 FIN
295*LBL 58
1.74 STO 13 FIN
299*LBL 59
1.74 STO 13 FIN
303*LBL 60
1.74 STO 13 FIN
307*LBL 61
1.74 STO 13 FIN
311*LBL 62
1.74 STO 13 FIN
315*LBL 63
1.74 STO 13 FIN
319*LBL 64
1.74 STO 13 FIN
323*LBL 65
1.74 STO 13 FIN
327*LBL 66
1.74 STO 13 FIN
331*LBL 67
1.74 STO 13 FIN
335*LBL 68
1.74 STO 13 FIN
339*LBL 69
1.74 STO 13 FIN
343*LBL 70
1.74 STO 13 FIN
347*LBL 71
1.74 STO 13 FIN
351*LBL 72
1.74 STO 13 FIN
355*LBL 73
1.74 STO 13 FIN
359*LBL 74
1.74 STO 13 FIN
363*LBL 75
1.74 STO 13 FIN
367*LBL 76
1.74 STO 13 FIN
371*LBL 77
1.74 STO 13 FIN
375*LBL 78
1.74 STO 13 FIN
379*LBL 79
1.74 STO 13 FIN
383*LBL 80
1.74 STO 13 FIN
387*LBL 81
1.74 STO 13 FIN
391*LBL 82
1.74 STO 13 FIN
395*LBL 83
1.74 STO 13 FIN
399*LBL 84
1.74 STO 13 FIN
403*LBL 85
1.74 STO 13 FIN
407*LBL 86
1.74 STO 13 FIN
411*LBL 87
1.74 STO 13 FIN
415*LBL 88
1.74 STO 13 FIN
419*LBL 89
1.74 STO 13 FIN
423*LBL 90
1.74 STO 13 FIN
427*LBL 91
1.74 STO 13 FIN
431*LBL 92
1.74 STO 13 FIN
435*LBL 93
1.74 STO 13 FIN
439*LBL 94
1.74 STO 13 FIN
443*LBL 95
1.74 STO 13 FIN
447*LBL 96
1.74 STO 13 FIN
451*LBL 97
1.74 STO 13 FIN
455*LBL 98
1.74 STO 13 FIN
459*LBL 99
1.74 STO 13 FIN
463*LBL 100
1.74 STO 13 FIN
467*LBL 101
1.74 STO 13 FIN
471*LBL 102
1.74 STO 13 FIN
475*LBL 103
1.74 STO 13 FIN
479*LBL 104
1.74 STO 13 FIN
483*LBL 105
1.74 STO 13 FIN
487*LBL 106
1.74 STO 13 FIN
491*LBL 107
1.74 STO 13 FIN
495*LBL 108
1.74 STO 13 FIN
499*LBL 109
1.74 STO 13 FIN
503*LBL 110
1.74 STO 13 FIN
507*LBL 111
1.74 STO 13 FIN
511*LBL 112
1.74 STO 13 FIN
515*LBL 113
1.74 STO 13 FIN
519*LBL 114
1.74 STO 13 FIN
523*LBL 115
1.74 STO 13 FIN
527*LBL 116
1.74 STO 13 FIN
531*LBL 117
1.74 STO 13 FIN
535*LBL 118
1.74 STO 13 FIN
539*LBL 119
1.74 STO 13 FIN
543*LBL 120
1.74 STO 13 FIN
547*LBL 121
1.74 STO 13 FIN
551*LBL 122
1.74 STO 13 FIN
555*LBL 123
1.74 STO 13 FIN
559*LBL 124
1.74 STO 13 FIN
563*LBL 125
1.74 STO 13 FIN
567*LBL 126
1.74 STO 13 FIN
571*LBL 127
1.74 STO 13 FIN
575*LBL 128
1.74 STO 13 FIN
579*LBL 129
1.74 STO 13 FIN
583*LBL 130
1.74 STO 13 FIN
587*LBL 131
1.74 STO 13 FIN
591*LBL 132
1.74 STO 13 FIN
595*LBL 133
1.74 STO 13 FIN
599*LBL 134
1.74 STO 13 FIN
603*LBL 135
1.74 STO 13 FIN
607*LBL 136
1.74 STO 13 FIN
611*LBL 137
1.74 STO 13 FIN
615*LBL 138
1.74 STO 13 FIN
619*LBL 139
1.74 STO 13 FIN
623*LBL 140
1.74 STO 13 FIN
627*LBL 141
1.74 STO 13 FIN
631*LBL 142
1.74 STO 13 FIN
635*LBL 143
1.74 STO 13 FIN
639*LBL 144
1.74 STO 13 FIN
643*LBL 145
1.74 STO 13 FIN
647*LBL 146
1.74 STO 13 FIN
651*LBL 147
1.74 STO 13 FIN
655*LBL 148
1.74 STO 13 FIN
659*LBL 149
1.74 STO 13 FIN
663*LBL 150
1.74 STO 13 FIN
667*LBL 151
1.74 STO 13 FIN
671*LBL 152
1.74 STO 13 FIN
675*LBL 153
1.74 STO 13 FIN
679*LBL 154
1.74 STO 13 FIN
683*LBL 155
1.74 STO 13 FIN
687*LBL 156
1.74 STO 13 FIN
691*LBL 157
1.74 STO 13 FIN
695*LBL 158
1.74 STO 13 FIN
699*LBL 159
1.74 STO 13 FIN
703*LBL 160
1.74 STO 13 FIN
707*LBL 161
1.74 STO 13 FIN
711*LBL 162
1.74 STO 13 FIN
715*LBL 163
1.74 STO 13 FIN
719*LBL 164
1.74 STO 13 FIN
723*LBL 165
1.74 STO 13 FIN
727*LBL 166
1.74 STO 13 FIN
731*LBL 167
1.74 STO 13 FIN
735*LBL 168
1.74 STO 13 FIN
739*LBL 169
1.74 STO 13 FIN
743*LBL 170
1.74 STO 13 FIN
747*LBL 171
1.74 STO 13 FIN
751*LBL 172
1.74 STO 13 FIN
755*LBL 173
1.74 STO 13 FIN
759*LBL 174
1.74 STO 13 FIN
763*LBL 175
1.74 STO 13 FIN
767*LBL 176
1.74 STO 13 FIN
771*LBL 177
1.74 STO 13 FIN
775*LBL 178
1.74 STO 13 FIN
779*LBL 179
1.74 STO 13 FIN
783*LBL 180
1.74 STO 13 FIN
787*LBL 181
1.74 STO 13 FIN
791*LBL 182
1.74 STO 13 FIN
795*LBL 183
1.74 STO 13 FIN
799*LBL 184
1.74 STO 13 FIN
803*LBL 185
1.74 STO 13 FIN
807*LBL 186
1.74 STO 13 FIN
811*LBL 187
1.74 STO 13 FIN
815*LBL 188
1.74 STO 13 FIN
819*LBL 189
1.74 STO 13 FIN
823*LBL 190
1.74 STO 13 FIN
827*LBL 191
1.74 STO 13 FIN
831*LBL 192
1.74 STO 13 FIN
835*LBL 193
1.74 STO 13 FIN
839*LBL 194
1.74 STO 13 FIN
843*LBL 195
1.74 STO 13 FIN
847*LBL 196
1.74 STO 13 FIN
851*LBL 197
1.74 STO 13 FIN
855*LBL 198
1.74 STO 13 FIN
859*LBL 199
1.74 STO 13 FIN
863*LBL 200
1.74 STO 13 FIN
867*LBL 201
1.74 STO 13 FIN
871*LBL 202
1.74 STO 13 FIN
875*LBL 203
1.74 STO 13 FIN
879*LBL 204
1.74 STO 13 FIN
883*LBL 205
1.74 STO 13 FIN
887*LBL 206
1.74 STO 13 FIN
891*LBL 207
1.74 STO 13 FIN
895*LBL 208
1.74 STO 13 FIN
899*LBL 209
1.74 STO 13 FIN
903*LBL 210
1.74 STO 13 FIN
907*LBL 211
1.74 STO 13 FIN
911*LBL 212
1.74 STO 13 FIN
915*LBL 213
1.74 STO 13 FIN
919*LBL 214
1.74 STO 13 FIN
923*LBL 215
1.74 STO 13 FIN
927*LBL 216
1.74 STO 13 FIN
931*LBL 217
1.74 STO 13 FIN
935*LBL 218
1.74 STO 13 FIN
939*LBL 219
1.74 STO 13 FIN
943*LBL 220
1.74 STO 13 FIN
947*LBL 221
1.74 STO 13 FIN
951*LBL 222
1.74 STO 13 FIN
955*LBL 223
1.74 STO 13 FIN
959*LBL 224
1.74 STO 13 FIN
963*LBL 225
1.74 STO 13 FIN
967*LBL 226
1.74 STO 13 FIN
971*LBL 227
1.74 STO 13 FIN
975*LBL 228
1.74 STO 13 FIN
979*LBL 229
1.74 STO 13 FIN
983*LBL 230
1.74 STO 13 FIN
987*LBL 231
1.74 STO 13 FIN
991*LBL 232
1.74 STO 13 FIN
995*LBL 233
1.74 STO 13 FIN
999*LBL 234
1.74 STO 13 FIN

```

TGT_ACQ PROGRAM LISTING (CONT'D)

```

325*LBL 31
XEQ 79 XEQ 81 XEQ 39
XEQ 59 RTN

331*LBL 32
XEQ 79 XEQ 82 XEQ 39
XEQ 59 RTN

337*LBL 33
XEQ 79 XEQ 83 XEQ 39
XEQ 59 RTN

343*LBL 34
XEQ 79 XEQ 84 XEQ 39
XEQ 59 RTN

349*LBL 35
XEQ 79 XEQ 85 XEQ 39
XEQ 59 RTN

355*LBL 40
XEQ 47 XEQ 81 XEQ 48
XEQ 82 XEQ 43 XEQ 87
XEQ 48 XEQ 84 XEQ 48
XEQ 85 XEQ 46 RTN

360*LBL 41
XEQ 47 XEQ 81 XEQ 48
RTN

373*LBL 42
XEQ 47 XEQ 82 XEQ 48
RTN

379*LBL 43
XEQ 47 XEQ 83 XEQ 48
RTN

385*LBL 44
XEQ 47 XEQ 84 XEQ 48
RTN

395*LBL 45
XEQ 47 XEQ 85 XEQ 48
RTN

397*LBL 47
XEQ 79 XEQ 20 XEQ 23
* STO 61 XEQ 24 SORT
XEQ 29 * XEQ 81 *
CHS EIX STO 61
*8-12 TRANS * APCL 01
RTN 3.512 XEQ 16 /
XEQ 11 * XEQ 24 *
CHS EIX STO 82
* VIS TRANS * APCL 02
RTN

405*LBL 61
*DETECTED* RTN .25
STO 10 RTN

431*LBL 82
*CLUT DETECT* RTN 1
STO 10 RTN

437*LBL 83
*CLASSIFIED* RTN 2
STO 10 RTN

443*LBL 84
*RECOGNIZED* RTN 4
STO 10 RTN

449*LBL 85
*IDENTIFIED* RTN 8
STO 10 RTN

455*LBL 47
*SEARCH FOR* PROMPT
STO 23 *RANGE* PROMPT
STO 20 RTN

463*LBL 49
XEQ 39 XEQ 60
*WHAT PROB* PROMPT
STO 22 XEQ 60 XEQ 79
XEQ 39 / 1 - THIS LN
CHS 3.4 * XEQ 23 *
XEQ 24 / XEQ 83
STO 04 *TIME* APCL 44
RTN 0.01 STOP
RTN

474*LBL 79
*RANGE* PROMPT STO 20
RTN

499*LBL 39
* STO 68 XEQ 24
XEQ 28 * STO 04
XEQ 20 SORT XEQ 29 *
XEQ 04 * STO 04
XEQ 07 XEQ 25 *
XEQ 04 - XEQ 26
XEQ 13 * XEQ 24
STO 09 XEQ 37 RTN

527*LBL 26
XEQ 29 XEQ 24 XEQ 25
XEQ 29 *RANGE*
APCL 06 RTN

533*LBL 29
XEQ 29 XEQ 06 SORT /
XEQ 26 * STO 04
XEQ 19 XEQ 10 *
XEQ 13 / XEQ 26 *
XEQ 04 * STO 04
XEQ 07 XEQ 25 *
XEQ 04 / STO 06 RTN

561*LBL 37
XEQ 03 XEQ 10 /
XEQ 03 * 2.7 *
STO 04 XEQ 03 XEQ 04
XEQ 02 1 +
XEQ 02 / 1/X STO 08
RTN

563*LBL 39
XEQ 39 XEQ 60
*WHAT PROB* PROMPT
STO 22 XEQ 60 XEQ 79
XEQ 39 / 1 - THIS LN
CHS 3.4 * XEQ 23 *
XEQ 24 / XEQ 83
STO 04 *TIME* APCL 44
RTN 0.01 STOP
RTN

574*LBL 79
*RANGE* PROMPT STO 20
RTN

599*LBL 39
* STO 68 XEQ 24
XEQ 28 * STO 04
XEQ 20 SORT XEQ 29 *
XEQ 04 * STO 04
XEQ 07 XEQ 25 *
XEQ 04 - XEQ 26
XEQ 13 * XEQ 24
STO 09 XEQ 37 RTN

627*LBL 26
XEQ 29 XEQ 24 XEQ 25
XEQ 29 *RANGE*
APCL 06 RTN

633*LBL 29
XEQ 29 XEQ 06 SORT /
XEQ 26 * STO 04
XEQ 19 XEQ 10 *
XEQ 13 / XEQ 26 *
XEQ 04 * STO 04
XEQ 07 XEQ 25 *
XEQ 04 / STO 06 RTN

661*LBL 37
XEQ 03 XEQ 10 /
XEQ 03 * 2.7 *
STO 04 XEQ 03 XEQ 04
XEQ 02 1 +
XEQ 02 / 1/X STO 08
RTN

663*LBL 39
XEQ 39 XEQ 60
*WHAT PROB* PROMPT
STO 22 XEQ 60 XEQ 79
XEQ 39 / 1 - THIS LN
CHS 3.4 * XEQ 23 *
XEQ 24 / XEQ 83
STO 04 *TIME* APCL 44
RTN 0.01 STOP
RTN

674*LBL 79
*RANGE* PROMPT STO 20
RTN

699*LBL 39
* STO 68 XEQ 24
XEQ 28 * STO 04
XEQ 20 SORT XEQ 29 *
XEQ 04 * STO 04
XEQ 07 XEQ 25 *
XEQ 04 - XEQ 26
XEQ 13 * XEQ 24
STO 09 XEQ 37 RTN

727*LBL 26
XEQ 29 XEQ 24 XEQ 25
XEQ 29 *RANGE*
APCL 06 RTN

733*LBL 29
XEQ 29 XEQ 06 SORT /
XEQ 26 * STO 04
XEQ 19 XEQ 10 *
XEQ 13 / XEQ 26 *
XEQ 04 * STO 04
XEQ 07 XEQ 25 *
XEQ 04 / STO 06 RTN

761*LBL 37
XEQ 03 XEQ 10 /
XEQ 03 * 2.7 *
STO 04 XEQ 03 XEQ 04
XEQ 02 1 +
XEQ 02 / 1/X STO 08
RTN

763*LBL 39
XEQ 39 XEQ 60
*WHAT PROB* PROMPT
STO 22 XEQ 60 XEQ 79
XEQ 39 / 1 - THIS LN
CHS 3.4 * XEQ 23 *
XEQ 24 / XEQ 83
STO 04 *TIME* APCL 44
RTN 0.01 STOP
RTN

774*LBL 79
*RANGE* PROMPT STO 20
RTN

799*LBL 39
* STO 68 XEQ 24
XEQ 28 * STO 04
XEQ 20 SORT XEQ 29 *
XEQ 04 * STO 04
XEQ 07 XEQ 25 *
XEQ 04 - XEQ 26
XEQ 13 * XEQ 24
STO 09 XEQ 37 RTN

827*LBL 26
XEQ 29 XEQ 24 XEQ 25
XEQ 29 *RANGE*
APCL 06 RTN

833*LBL 29
XEQ 29 XEQ 06 SORT /
XEQ 26 * STO 04
XEQ 19 XEQ 10 *
XEQ 13 / XEQ 26 *
XEQ 04 * STO 04
XEQ 07 XEQ 25 *
XEQ 04 / STO 06 RTN

861*LBL 37
XEQ 03 XEQ 10 /
XEQ 03 * 2.7 *
STO 04 XEQ 03 XEQ 04
XEQ 02 1 +
XEQ 02 / 1/X STO 08
RTN

863*LBL 39
XEQ 39 XEQ 60
*WHAT PROB* PROMPT
STO 22 XEQ 60 XEQ 79
XEQ 39 / 1 - THIS LN
CHS 3.4 * XEQ 23 *
XEQ 24 / XEQ 83
STO 04 *TIME* APCL 44
RTN 0.01 STOP
RTN

874*LBL 79
*RANGE* PROMPT STO 20
RTN

899*LBL 39
* STO 68 XEQ 24
XEQ 28 * STO 04
XEQ 20 SORT XEQ 29 *
XEQ 04 * STO 04
XEQ 07 XEQ 25 *
XEQ 04 - XEQ 26
XEQ 13 * XEQ 24
STO 09 XEQ 37 RTN

927*LBL 26
XEQ 29 XEQ 24 XEQ 25
XEQ 29 *RANGE*
APCL 06 RTN

933*LBL 29
XEQ 29 XEQ 06 SORT /
XEQ 26 * STO 04
XEQ 19 XEQ 10 *
XEQ 13 / XEQ 26 *
XEQ 04 * STO 04
XEQ 07 XEQ 25 *
XEQ 04 / STO 06 RTN

961*LBL 37
XEQ 03 XEQ 10 /
XEQ 03 * 2.7 *
STO 04 XEQ 03 XEQ 04
XEQ 02 1 +
XEQ 02 / 1/X STO 08
RTN

963*LBL 39
XEQ 39 XEQ 60
*WHAT PROB* PROMPT
STO 22 XEQ 60 XEQ 79
XEQ 39 / 1 - THIS LN
CHS 3.4 * XEQ 23 *
XEQ 24 / XEQ 83
STO 04 *TIME* APCL 44
RTN 0.01 STOP
RTN

974*LBL 79
*RANGE* PROMPT STO 20
RTN

999*LBL 39
* STO 68 XEQ 24
XEQ 28 * STO 04
XEQ 20 SORT XEQ 29 *
XEQ 04 * STO 04
XEQ 07 XEQ 25 *
XEQ 04 - XEQ 26
XEQ 13 * XEQ 24
STO 09 XEQ 37 RTN

```

DISTRIBUTION FOR NV&EOL REPORT DELNV-TR-0030

No. Copies	Addressee	No. Copies	Addressee
20	Commander FRADCOM ATTN: DRDEL-AP-OA M. Geisler Adelphi, MD 20783	1	Project Manager M60 Tank System Warren, MI 48090
1	Director Atmospheric Sciences Lab ATTN: DELAS-D White Sands Missile Range, NM 88002	1	Project Manager MICV Warren, MI 48090
1	Director CS&TA Laboratory ATTN: DELCS-D Fort Monmouth, NJ 07703	1	Project Manager TOW/DRAGON Redstone Arsenal, AL 35809
1	Director Electronic Warfare Lab ATTN: DELEW-D Fort Monmouth, NJ 07703	1	Project Manager GLLD/LTD Redstone Arsenal, AL 35809
1	Director Electronics Technology and Devices Lab ATTN: DELET-D Fort Monmouth, NJ 07703	1	Project Manager VIPER AHAMS Redstone Arsenal, AL 35809
1	Commander Harry Diamond Labs ATTN: DELHD-AC Adelphi, MD 20783	1	Project Manager AAH AVARADCOM St. Louis, MO 63166
1	Director Signal Warfare Lab ATTN: DELSW-D Vint Hill Station, VA 22186	1	Project Manager TADS/PNVS AVARADCOM St. Louis, MO 63166
1	Project Manager XM-1 Tank System Warren, MI 48090	1	Commander ARRCOM ATTN: DRSAR-CPI Rock Island, IL 61299
		1	Project Manager RPV AVARADCOM St. Louis, MO 63166
		1	Commander ARRADCOM ATTN: DRDAR-SEC Dover, NJ 07801

No. Copies	Addressee	No. Copies	Addressee
1	Commander CORADCOM ATTN: DRDCO-PPACA Fort Monmouth, NJ 07703	1	Commander NARADCOM ATTN: DRDNA-O Natick, MA 01760
1	Commander CERCOM ATTN: DRSEL-CP-CR Fort Monmouth, NJ 07703	1	Commander AMMRC Watertown, MA 02172
1	Commander MERADCOM ATTN: DRDMI-CA	1	Commandant US Army Infantry School Ft. Benning, GA 31905
3	ATTN: DRDMI-WP Fort Belvoir, VA 22060	1	Director Defense Advanced Research Projects Agency Rosslyn, VA 22209
1	Commander MIRADCOM ATTN: DRDMI-DC Redstone Arsenal, AL 35809	1	Commander US Naval Research Lab Washington, DC 20375
1	Commander MIRCOM ATTN: DRSMI-FO Redstone Arsenal, AL 35809	1	Commander HQ DARCOM ATTN: DRCCP-E Alexandria, VA 22333
1	Commander AVARADCOM ATTN: DRCAV-BC St. Louis, MO 63166	1	Commandant Defense Systems Management School Fort Belvoir, VA 22060
1	Commander TSARCOM ATTN: DRSTS-CO St. Louis, MO 63166	1	Commandant US Army Engineer School Fort Belvoir, VA 22060
1	Commander TARADCOM ATTN: DRCTA-VC Warren, MI 48090	1	Commander US Operational Test and Evaluation Agency Fort Belvoir, VA 22060
1	Commander TARCOM ATTN: DRSTA-NC Warren, MI 48090	1	Commander USACSC Fort Belvoir, VA 22060

No. Copies	Addressee	No. Copies	Addressee
1	HQDA ATTN: DACACA Washington, DC 20310	1	Project Manger REMBASS ATTN: DRCPM-RBS Fort Monmouth, NJ 07703
12	Defense Technical Info Ctr ATTN: DDC-TCA Cameron Station (Bldg 5) Alexandria, VA 22314	1	Project Manager FIREFINDER ATTN: DRCPM-FE Fort Monmouth, NJ 07703
1	Commander US Army Training & Doctrine Cnd ATTN: ATCD-AN Fort Monroe, VA 23651	1	Department of Defense Production Engineering Spt Ofc (PESO) ATTN: D. Anderson Cameron Station Alexandria, VA 22314
2	Commander US Army Logistics Ctr Fort Lee, VA 23801	1	Project Manager CAC ATTN: DRCPM-CAC Vint Hill Station, VA 22186
1	Commander US Army Systems Analysis Agency Aberdeen Proving Ground, MD 21005	1	Project Manager SOTAS ATTN: DRCPM-STIA Fort Monmouth, NJ 07703
1	NASA Scientific & Tech Info Facility ATTN: Acquisitions Branch (S-AK/DL) P.O. Box 33 College Park, MD 20740	1	Commandant US Army Armor School Fort Knox, KY 40121
1	Study Center National Maritime Research Ctr King's Point, NY 11024	1	Commandant US Army Field Artillery School Fort Sill, OK 73503
1	Commander USAAVNC Fort Rucker, AL 36362	1	Commandant US Army Air Defense School Fort Bliss, TX 79916
1	Director NV&EOL ATTN: DELNU-TMS, SIMCO Fort Belvoir, VA 22060	1	Director US Army Air Mobility R&D Ctr Ames Research Ctr Moffett Field, CA 94035

No. Copies	Addressee	No. Copies	Addressee
3	Commander AFSC/ACC Andrews AFB, MD 20334	1	Director TRASANA White Sands Missile Range, NM 88002
2	Commander ESD/ACC Hanscomb AFB, MA 01730	1	Commander USA MICOM Redstone Arsenal, AL 35809
1	Commander US Naval Ordnance Lab/White Oak ATTN: Technical Library Silver Spring, MD 20910	1	Commander CORADCOM ATTN: DRDCO-PPA-CA Fort Monmouth, NJ 07703
1	Commander Naval Electronics Lab Ctr ATTN: Library San Diego, CA 92152	1	Commander CERCOM ATTN: DRSEL-CP-CR Fort Monmouth, NJ 07703
1	Armament Development and Test Ctr ATTN: DLOSL, Tech Library Eglin Air Force Base, FL 32542	1	Commander AVARADCOM ATTN: DRCV-BC St. Louis, MO 63166
40	Director NV&EOL ATTN: DELNV-VI Fort Belvoir, VA 22060	1	Commander TSARCOM ATTN: DRSTS-CO St. Louis, MO 63166
1	Commander Sacramento Army Depot Sacramento, CA 95813	1	Commander TARADCOM ATTN: DRCTA-VC Warren, MI 48090
1	Commander New Cumberland Army Depot New Cumberland, PA 17070	1	Commander TARCOM ATTN: DRSTA-NC Warren, MI 48090
1	Commander Anniston Army Depot Anniston, AL 36201	1	Commander NARADCOM ATTN: DRDNA-O Natick, MA 01760
1	Dept of Defense Production Engineering Spt Otc (PESO) ATTN: H.K. MacKechne Cameron Station Alexandria, VA 22314		

No. Copies	Addressee	No. Copies	Addressee
1	Commander AMMRC Watertown, MA 02172	1	Commander US Army Training & Doctrine Com ATTN: ATCD-AN Fort Monroe, VA 23651
1	Commander US Army Infantry School Fort Benning, GA 31905	2	Commander US Army Logistics Ctr Fort Lee, VA 23801
1	Director Defense Advanced Research Projects Agency Rosslyn, VA 22209	8	Commander US Army Systems Analysis Agency Aberdeen Proving Ground, MD 21005
1	Commander US Naval Research Lab Washington, DC 20375	1	Commander USAAVNC Fort Rucker, AL 36362
1	Commander HQ DARCOM ATTN: DRCCP-E Alexandria, VA 22333	1	Director NV&EOL ATTN: DELNV-TMS/SEMCO Fort Belvoir, VA 22060
1	Commandant Defense Systems Management School Fort Belvoir, VA 22060	1	Project Manager REMBASS ATTN: DRCPM-RBS Fort Monmouth, NJ 07703
1	Commandant US Army Engineer School Fort Belvoir, VA 22060	1	Project Manager FIREFINDER ATTN: DRCPM-FF Fort Monmouth, NJ 07703
1	Commander US Operational Test and Evaluation Agency Fort Belvoir, VA 22060	1	Project Manager CAC ATTN: DRCPM-CAC Vint Hill Station, VA 22186
1	Commander USACSC Fort Belvoir, VA 22060	1	Project Manager SOTAS ATTN: DRCPM-STA Fort Monmouth, NJ 07703
1	HQDA ATTN: DACA-CA Washington, DC 20310		

No. Copies	Addressee	No. Copies	Addressee
1	Commandant US Army Armor Center and School ATTN: ATZK-CD-SD Fort Knox, KY 40121	1	Director Office of the Project Manager SMOKE ATTN: DRCPM-SMK (COL Eunie) Aberdeen Proving Ground, MD 21005
1	Commandant US Army Field Artillery School Fort Sill, OK 73503	1	Director US Army Waterways Experiment Station ATTN: WESEA (Lewis Link) P.O. Box 631 Vicksburg, MS
1	Commandant US Army Air Defense School Fort Bliss, TX 79916		
1	Director US Army Air Mobility R&D Ctr Ames Research Ctr Moffett Field, CA 94035	1	US Army Operational Test Evaluation Agency ATTN: CSTE-STS (Fred McCoy) 5600 Columbia Pike Falls Church, VA 22041
1	Commander AFSC/ACC Andrews AFB, MD 20334	1	Commander US Army Electronic Research and Development Command ATTN: CM/CCM (F. Manion) 2800 Powder Mill Road Adelphi, MD 20783
1	Commander ESD/ACC Hanscomb AFB, MA 01730		
1	Commander US Naval Ordnance Lab/White Oak ATTN: Technical Library Silver Spring, MD 20910	1	Commander US Tank Automotive Research and Development Command ATTN: DRDTA-ZS (Otto Renius) Warren, MI 48090
1	Commander Naval Electronics Lab Ctr ATTN: Library San Diego, CA 92152	1	USA Headquarters ATTN: ATCD-IE-R (Mr. Ingram) Fort Monroe, VA 23651
1	Armament Development & Test Ctr ATTN: DLOSL Tech Library Eglin Air Force Base, FL 32542	3	Commander USA Atmospheric Sciences Lab ATTN: DELAS-EO (Dr. F. Niles) White Sands Missile Range, NM 88002
1	Harry Diamond Lab ATTN: DELHD-R-C (Dr. D. Giglio) 2800 Powder Mill Road Adelphi, MD 20783		

No. Copies	Addressee	No. Copies	Addressee
3	Headquarters DA ATTN: DAMI-ISPC (Mr. J. Beck) PENTAGON Washington, DC 20310	1	Commander USA Atmospheric Sciences Lab ATTN: DELAS-EO (Dr. L. Duncan) White Sands Missile Range, NM 88002
1	HQ ARRADCOM ATTN: DRADAR-SEA (Dr. R.J. Moore) Dover, NJ 07801	1	Commander USA MICOM ATTN: DRSMI-IEO (R&D) (Mr. G. Wiedenhofer) Redstone Arsenal, AL 35809
1	Commander, USAARRADCOM CSL ATTN: DRDAR-CLB-PS (Steubing) Aberdeen Proving Ground, MD 21010	1	Commander USA OTEA 5600 Columbia Pike Falls Church, VA
1	PM Smoke/Obscurants ATTN: DRCPM-SMK-T (J. G. Nelson) Aberdeen Proving Ground, MD 21005	1	Commander NRL Code 8320 ATTN: L. H. Ruhnke Washington, DC 20375
1	Director AMSAA ATTN: DRXSY-GPL (Mr. F. Campbell) Aberdeen Proving Ground, MD 21005	1	Commander USA OTEA ATTN: Mr. Fred McCoy 5600 Columbia Pike Falls Church, VA
1	Commander USA Test & Evaluation Command ATTN: DRSTE-AD-M (W. Baity) Aberdeen Proving Ground, MD 21005	1	Commander USA Ballistics Research Lab ATTN: DRDAR-BLB (A. LaGrange) Aberdeen Proving Ground, MD 21005
1	Commander USA Combined Arms Center ATTN: CACDA-CCA (Mr. K. Pickett) Fort Leavenworth, KS 66027	1	Commander USA Concepts Analysis Agency ATTN: MOCA-SMC (Mr. Hal Hock) 8120 Woodmont Ave Bethesda, MD 21004
1	Mr. Lucien Biberman Institute of Defense Analysis Science & Technology Div 400 Army-Navy Drive Arlington, VA 22202		

No. Copies	Addressee	No. Copies	Addressee
1	TRADOC Systems Analysis Agency ATTN: ATAA-TDB (Mr. L. Dominguez) White Sands Missile Range, NM 88002	1	Director AMSAA ATTN: DRASY-S (M. Reches) Aberdeen Proving Ground, MD 21005
1	TRADOC Systems Analysis Agency ATTN: ATAA-D (Mr. W. Payne) White Sands Missile Range, NM 88002	1	HQDA ATTN: DAMA-ARZ-D (Dr. F. Verderame) Pentagon Washington, DC 20310
1	Commander USA TRADOC ATTN: ATCD-TFC (Dr. M.P. Pastel) Fort Monroe, VA 23651	1	Commander Naval Weapons Center ATTN: Dr. Alex Shlanta Code 3918 China Lake, CA 93555
1	Commander ASD/ENASC ATTN: (Larry J. Beasley) Wright-Patterson AFB, OH 45433	1	Commander HDL ATTN: DELHD-SD (Dr. W. Pepper) 2800 Powder Mill Rd Adelphi, MD 20783
1	Commanding Officer Naval Intelligence Support Ctr ATTN: NISC (Code 43) (H. F. St. Aubin) 4301 Suitland Rd Suitland, MD 20390	1	Commander USAMERADCOM ATTN: DRDME-RT (O. Fred Kezer) Fort Belvoir, VA 22060
1	Commander USA MICOM ATTN: DRSMI-OGA (Dr. B. Fowler) Redstone Arsenal, AL 35809	1	Commander Naval Surface Weapons Center ATTN: Diana L. Shamblain Code DG-302 Dahlgren, VA 22448
1	The Rand Corporation ATTN: Mr. R. Huschke 1700 Main St. Santa Monica, CA 90406	1	Commander USA Combined Arms Center Developments Activity ATTN: ATZL-CA-TM-K (Maj. C. R. Otto) Fort Leavenworth, KS 66026
1	Commander USAMICOM ATTN: DRCPM-HF-GLD (M. E. Davis) Redstone Arsenal, AL 35809		

No. Copies	Addressee	No. Copies	Addressee
1	Commander Marine Corps Development Ctr ATTN: (FPR) MEDEC (Capt L. Martin) Quantico, VA 22134	1	Commander USA Combined Arms Combat Development Activity ATTN: ATZLCA-SAN (R. E. DeKinder, Jr.) Fort Leavenworth, KS 66027
1	Commander Dugway Proving Ground ATTN: STEDP-MT (Dr. L. Solomon) Dugway, UT 84022	1	Commander Atmospheric Sciences Lab ATTN: DELAS-EO-MO White Sands Missile Range, NM 88002
1	Commander Tactical Air Command ATTN: DRP (Maj McCann) Langley AFB, VA 23665	1	PM AAH ATTN: DRCPM-AAH-TM-S (Mr. Reago) St. Louis, MO 63166
1	Director Oklahoma State Field Office ATTN: Dr. C H. Arpke P.O. Box 1925 Eglin AFB, FL 32542	1	Deputy Under Secretary of the Army (Operations Research) ATTN: Mr. Woodall HQDA PENTAGON Washington, DC 20310
1	Commandant USA Field Artillery School ATTN: ATSF-GDRA (Jack J. Price) Ft. Sill, OK 73503	1	Deputy Under Secretary of the Army (Operations Research) ATTN: Dr. Fallin HQDA PENTAGON Washington, DC 20310
1	Commander USATRADOCC ATTN: ATCD-Z (H. Upton) Fort Monroe, VA 23651	1	HQ DA ODCSOPS ATTN: DAMO-RQD (C. Collat) Washington, DC 20310
1	USA Chem School ATTN: ATZN-CM-CDM (J. Scully) Fort McClellan, AL 36205	1	HQDA ATTN: DAMA-CSS-C (LTC R. Bills) Washington, DC 20310
1	Commander Naval Air Systems Command ATTN: Code Air 310C (Dr. H. Rosenwasser) Washington, DC 20361		

No. Copies	Addressee	No. Copies	Addressee
1	Director Defense Intelligence Agency ATTN: DT-1A (Mr. Berler) PENTAGON Washington, DC 20310	1	Commander USAMICOM ATTN: DRDME-REW (Mr. H. Anderson) Redstone Arsenal, AL 35809
3	Commandant US Army Infantry Center and School ATTN: ATSH-CD-CS (OR/SA) (Dr. Dyer) Fort Benning, GA 31905	1	Commander Harry Diamond Labs ATTN: DELHD-RAC (R. Humphrey) 2800 Powder Mill Rd Adelphi, MD 20783
1	ATTN: ATSH-CD-MS-F (Cpt R. Copeland)	1	Air Force Geophysics Labs OPA (ATTN: Dr. R. Fenn) Hanscom AFB, MA 01731
1	ATTN: ATSH-CD-MS-E (Mr. McKenna)	1	Air Force Geophysics Labs OPA (ATTN: Dr. R. McClatchey) Hanscom AFB, MA 01731
1	Commander USA Engineer Waterways Experimental Station ATTN: Mr. G. Lundien Vicksburg, MS 39180	1	Director Advanced Research Projects Agency ATTN: Dr. J. Tegnalia 1400 Wilson Blvd Arlington, VA 22209
1	USAF Airstaff Directorate of Concepts PENTAGON ATTN: Maj E. Duff Washington, DC 20310	1	Aerodyne Research, Inc. Bedford Research Park ATTN: Dr. J. Ebersole Crosby Dr. Bedford, MA 01730
1	USAF Airstaff Directorate of Concepts and Analysis PENTAGON ATTN: Special Assistant for Weather (Maj E. Kolzynski) Rm 1D380B Washington, DC 20310	1	Commander USAARRADCOM Chemical Systems Lab ATTN: DRDAR-CLY-A (R. O. Pennsyle) Aberdeen Proving Ground, MD 21010
1	Commander USAIRADOC Systems Analysis Activity ATTN: ATAA-TFM (Mr. H. McCoy) White Sands Missile Range, NM 88002	1	Commander President USA Armor & Engineer Board ATTN: ATZK-AE-AR Fort Knox, KY 40121

No. Copies	Addressee	No. Copies	Addressee
1	Director Defense Intelligence Agency ATTN: DT-1A (Mr. Berler) PENTAGON Washington, DC 20310	1	Commander USAMICOM ATTN: DRDMI-REW (Mr. H. Anderson) Redstone Arsenal AL 35809
3	Commandant US Army Infantry Center and School ATTN: ATSH-CD-CS (OR/SA) (Dr. Dyer) Fort Benning, GA 31905	1	Commander Harry Diamond Labs ATTN: DE-LHD-RAC (R. Humphrey) 2800 Powder Mill Rd Adelphi, MD 20783
1	ATTN: ATSH-CD-MS-F (Cpt R. Copeland)	1	Air Force Geophysics Labs OPA (ATTN: Dr. R. Fenn) Hanscom AFB, MA 01731
1	ATTN: ATSH-CD-MS-E (Mr. McKenna)	1	Air Force Geophysics Labs OPA (ATTN: Dr. R. McClatchey) Hanscom AFB, MA 01731
1	Commander USA Engineer Waterways Experimental Station ATTN: Mr. G. Lundien Vicksburg, MS 39180	1	Director Advanced Research Projects Agency ATTN: Dr. J. Tegnella 1400 Wilson Blvd Arlington, VA 22209
1	USAF Airstaff Directorate of Concepts PENTAGON ATTN: Maj E. Duff Washington, DC 20310	1	Aerodyne Research, Inc. Bedford Research Park ATTN: Dr. J. Ebersole Crosby Dr. Bedford, MA 01730
1	USAF Airstaff Directorate of Concepts and Analysis PENTAGON ATTN: Special Assistant for Weather (Maj E. Kolzynski) Rm 1D380B Washington, DC 20310	1	Commander USAARRADCOM Chemical Systems Lab ATTN: DRDAR-CLY-A (R. O. Pennsyle) Aberdeen Proving Ground, MD 21010
1	Commander USATRADOC Systems Analysis Activity ATTN: ATAA-TEM (Mr. H. McCoy) White Sands Missile Range, NM 88002	1	Commander President USA Armor & Engineer Board ATTN: ATZK-AE-AR Fort Knox, KY 40121

No. Copies	Addressee	No. Copies	Addressee
1	Naval Research Lab Code 1409 ATTN: Dr. J. MacCallum Washington, DC 20375	1	Andrulis Research Corp. ATTN: Mr. Carr 7315 Wisconsin Ave Suite 650N Bethesda, MD 20014
1	Commander USA Missile Command ATTN: DRCPM-TOE (Mr. C. Jackson) Redstone Arsenal, AL 35809	1	USA FSTC ATTN: DRXST-ESI (Mennerick) 220 7th St NE Charlottesville, VA 22901
1	Commander DARCOM ATTN: DRCLDC (Dr. J. Bender) 5001 Eisenhower Ave Alexandria, VA 22333	1	Director USAHEL ATTN: DRXHE-CC (Sy Steinberg) Aberdeen Proving Ground, MD 21005
1	Commander USATRAIDOC ATTN: ATCD-JR (S. Goldberg) Fort Monroe, VA 22651	1	Honeywell, Inc. ATTN: Mr. Paul W. Kruse 10701 Lyndale Avenue South Bloomington, MN 55420
1	Joint AMC/NMC/AFLC/AFSC Commanders Joint Technical Coordinating Group for Munitions Effectiveness ATTN: DRXSY-FJ (Mr. James O'Bryon) Aberdeen Proving Ground, MD	1	McDonald Douglass Corp. ATTN: Mr. Michael Johnson Dept 313 PO 516 St. Louis, MO
1	Commander US Army CACDA ATTN: ATZLCA-WE (LTC Taylor) Fort Leavenworth, KS 66027	1	Director BRL ATTN: DR-DAR-BLV (J.E. Camerer) Aberdeen, MD 21005
1	Naval Weapons Support Ctr Code 502 (Mr. Carl Lohkemp) Crane, IN 47522	1	AFGL/OPI Mail Stop 30 (Robert McClatchey) Hanscom AFB Bedford, MA 01731
1	Honeywell, Inc. Systems & Research Center Aerospace & Defense Group (Mr. Raymond Schaefer) 2600 Ridgway Parkway Minneapolis, MN 55413	1	Director AMSAA ATTN: DRXSY-GB (John Kramer) Aberdeen Proving Ground, MD 21005

No. Copies	Addressee	No. Copies	Addressee
1	Commander US Army Infantry School ATTN: ATSH-CD-CS (CPT D. George) Fort Benning, GA 31905	1	Commander US Army Intelligence Ctr and School ATTN: ATSI-CD-CS (Mr. Cundy) Fort Huachuca, AZ 85613
1	Commander USAF TAWC/THL ATTN: Maj J. D. Kittrell Eglin Air Force Base, FL 32542	1	FS&TC ATTN: MT3 (F. A. Poleski) 229 Seventh Street NE Charlottesville, VA 22901
1	Commander USAF AWS/DNDP ATTN: CPT J. Kahler Scott Air Force Base, IL 62225	1	Naval EOD Facility ATTN: Technical Director, L. Dickinson Indian Head, MD 20640
1	NASEASYS COM Code SEA-62Y21 (LCDR William E. Major) Washington, DC 20350	2	USA CRREL ATTN: G. Aitken & Sid Gerard Hanover, NH 03755
1	Naval Research Laboratory Code 6532 ATTN: Dr. G. Trusty Washington, DC 20375	1	USA Medical Bioengineering Res and Dev Lab ATTN: LTC D. Gensler Fort Detrick, MD 21701
1	Naval Research Laboratory Code 6530 ATTN: J. Curcio Washington, DC 20375	1	Dept of Air Force Headquarters Air Weather Service (MAC) ATTN: DOOF (Maj Wright, 2015) Scott AFB, IL 62225
1	Commander ERADCOM ATTN: DRDEL-CT (Mr. John Johnson) Adelphi, MD 20783	1	Commander Dept of Army Headquarters TRADOC Combined Arms Test Activity ATTN: ATCAT-SCI (Dr. Darrell Collier) Fort Hood, TX 76544
1	Director AMSAA ATTN: DRXSY-GB (Mr. John W. Kramer) Aberdeen Proving Ground, MD 21005	1	Commander Defense Mapping School ATTN: Capt Cornwell Fort Belvoir, VA 22060

No. Copies	Addressee	No. Copies	Addressee
1	Commander USA Combat Development Experimentation Command ATTN: ATFC-PL-M (Gary Love) Fort Ord, CA 93941	1	Varo Inc., Texas Division 2201 Walnut St. Garland, TX 75040
1	Director Engineer Topographic Lab ATTN: Paul Krause Fort Belvoir, VA 22060	1	Systems & Applied Sciences Corp. ATTN: James R. Norton 6811 Kenilworth Ave Riverdale, MD 20840
1	Offices Deputy Undersecretary of Defense for Research and Advanced Technology (I&TS) ATTN: John McCallum Rm3D1079 PENTAGON Washington, DC 20301	1	Hughes Aircraft Company ATTN: Stuart H. Klapper Electro-Optical and Data Systems Group Culver City, CA 90230
2	Commander US Army Missile Command ATTN: DRCPM-CF (Col. H. E. Stubbs) Redstone Arsenal, AL 35898	1	Headquarters Air Weather Services ATTN: Army Liaison Scott AFB, IL 62225
1	Commander USAMICOM ATTN: DRCPM-MPE (Dick Dudney) Redstone Assenal, AL 35898	1	Lawrence Livermore National Lab Mail Stop L-9 (Frank Skidmore) P.O. Box 808 Livermore, CA 94550
1	Director Night Vision & Electro- Optics Laboratory ATTN: DELNV-V (Frank Shields) Fort Belvoir, VA 22060	50	Director Night Vision & Electro- Optics Laboratory ATTN: DELNV-V Fort Belvoir, VA 22060
1	Commander DCD, USA AVNC ATTN: Study Group I-ATZQ-D-CD Fort Rucker, AL 36362	2	DCS Corp. 1117 North 19th Street Suite 1101 Arlington, VA 22209
1	OSD (PA&E)(LSD) ATTN: Maj. Mayer Rm. 2B256 Pentagon Washington, DC 20301	2	E-OIR Measurements Associate P.O. Box 3348 College Station Fredericksburg, VA 22401
		1	Hughes Aircraft Company ATTN: Richard Janik Electro-Optical and Data Systems Group Culver City, CA 90230

FILMED

7-8